MARIA ROYAL

v1.05 · User Guide

Eight Maria robots and tools in one Expert Advisor: Antimartingale, Breakout, News, Trade Manager, Copier, Telegram, Maria AI and Maria Tools

MetaTrader 4 · a MetaTrader 5 version is also available



Website: https://polymaria.net
Telegram: https://t.me/polymaria_net
Author: Murodillo Eshkuvvatov
Edition: November 2026

Contents

1. About PolyMaria 3
2. What Maria Royal does 4
3. Installation 6
4. Quick start (5 steps) 8
5. The Maria Royal panel 9
6. Maria Antimartingale 11
7. Maria Breakout 14
8. Maria News 17
9. Maria Trade Manager 20
10. Maria Copier 24
11. Maria Telegram 27
12. Maria AI 30
13. Maria Tools 33
14. Tips: using the projects together 35
15. Settings reference 36
16. Troubleshooting 58
17. Risk warning 59
18. Support and links 59

1. About PolyMaria

PolyMaria (polymaria.net) is a home for MetaTrader traders. On polymaria.net you find the Maria robot family, thousands of robots, indicators and scripts for MT4 and MT5, free trading books, the Robot Builder and the PolyMaria desktop app.

Every Maria product comes with a full user guide like this one and support on our Telegram channel.

Link	Address
Website	https://polymaria.net
Telegram channel	https://t.me/polymaria_net
All products on MQL5	https://www.mql5.com/en/users/murodillo/seller

2. What Maria Royal does

Maria Royal = eight Maria products in one Expert Advisor. Attach it once and pick the project for the panel. Each project works like the single Maria product.


The eight projects

Project	What it does	Magic number	Order comment
Maria Antimartingale	Two ladders: ANTI STOP orders with the trend + MARTIN LIMIT copies against it, equity target.	2610510	Anti B3 / Anti CB3
Maria Breakout	A ladder of BUY STOP and SELL STOP orders around the price (live ladder, zones, equity target).	2610520	Breakout ...
Maria News	A BUY STOP + SELL STOP grid before economic news, by hand or automatic from the calendar.	2610530	News... B01
Maria Trade Manager	One-click trade desk: lot by risk, SL / TP, breakeven, trailing, partial TP, daily guard.	2610540	Trade Manager
Maria Copier	Copies trades between MetaTrader terminals on the same computer (MASTER / SLAVE).	2610550	Copier <key>
Maria Telegram	Trade messages, reports, alerts and chart pictures to your Telegram.	2610560	(sends no orders)
Maria AI	Chat with an AI about the market, trade check, trade ideas and a trade coach.	2610570 (ideas 2610571)	AI idea
Maria Tools	Chart tools: moving averages, bands, Fibonacci, pivots, sessions, S/R, oscillators, supply / demand, neural forecast, Elliott waves, cluster view.	none (never trades)	-

Magic numbers above = Magic base 2610500 + the project offset (+10 ... +70). Projects never touch each other's orders.

Key ideas

- **One panel, one project.** Click the project name in the panel header to open the project list. The chosen project's panel takes the same place on the chart.
- **RUN rule.** Only the project on the panel opens new trades. The others just finish their open trades.
- **Own settings, own orders.** Every project keeps its own magic number, its own saved panel values and its own orders.
- **COMMON settings.** Chart style, order lines, slippage, max spread, session, drawdown stop and rebate: set once for every project.
- **Every setting is also an input.** All settings are on the Inputs tab too (easy Strategy Tester).
- **Light and dark theme.** One click switches all panels and the chart colours.
- **First attach.** The project list opens: choose a project.



The project list in the dark and the light theme (illustration).

3. Installation

Requirements

Item	Requirement
Platform	MetaTrader 4 (Maria Royal.ex4).
Symbol	Antimartingale, Breakout and News are made for gold (XAUUSD); they also run on other symbols. Trade Manager, Copier, Telegram, Maria AI and Maria Tools work on any symbol.
Timeframe	Any. Antimartingale and Breakout set the chart to their timeframe (M15 / M5) the first time you attach the robot.
Trading permission	The AutoTrading button must be ON and "Allow live trading" ticked in the robot's Common tab.
Internet	Only for News (calendar), Telegram and Maria AI. See d) below.

a) From the MQL5 Market

1. Buy or rent Maria Royal on the MQL5 Market.
2. In MetaTrader 4 open the Terminal window (Ctrl+T) and go to the Market tab.
3. Open Purchased and click Install next to Maria Royal.
4. The robot appears in the Navigator window under Expert Advisors → Market. Drag it onto a chart.

b) Manual file install on MT4

1. In MetaTrader 4 open File → Open Data Folder.
2. Open MQL4 → Experts and copy Maria Royal.ex4 there.
3. In the Navigator window, right-click Expert Advisors → Refresh.
4. Drag Maria Royal onto a chart. On the Common tab tick "Allow live trading", click OK and make sure the AutoTrading button is ON.

c) MetaTrader 5

A separate MT5 version (Maria Royal MT5) is available. Install it the same way: File → Open Data Folder → MQL5 → Experts, refresh the Navigator, attach the robot and switch the Algo Trading button ON. MT5 needs a HEDGING account.

d) Internet addresses (WebRequest)

Open Tools → Options → Expert Advisors, tick "Allow WebRequest for listed URL" and add the addresses of the projects you use:

Address	Needed for
https://nfs.faireconomy.media	Maria News (news table, Auto news) and Maria AI (news reminders, trade check, after-news explainer)
https://api.telegram.org	Maria Telegram, and Maria AI if you chat with it from Telegram
https://api.anthropic.com	Maria AI with Anthropic Claude
https://api.openai.com	Maria AI with OpenAI
https://api.deepseek.com	Maria AI with DeepSeek
https://news.google.com	Maria AI news headlines

Antimartingale, Breakout, Trade Manager, Copier and Maria Tools do not use the internet. Maria Copier needs the master and slave terminals on the same computer or VPS (they talk through the Common\Files folder).

> **TIP** To update the robot, replace the .ex4 file (or reinstall from the Market) and attach it again. The panel values of every project are kept for each symbol and Magic base.

4. Quick start (5 steps)

1. Attach **Maria Royal** to a chart (for the trading projects: XAUUSD). The project list opens.
2. Click a project, for example **MARIA ANTIMARTINGALE**. Its panel opens; the row of the chosen project is red in the list.
3. Open **COMMON SETTINGS** (bottom of the project list) once and check chart style, slippage, max spread, session and the drawdown stop.
4. Press **SETTINGS >** at the top of the panel (the same button in all 8 projects; it also opens by itself when you choose a project) and set the project up. Then use it as described in its chapter (START, PLACE, BUY, ...).
5. To change the project click its name in the header. Keep **RUN: ONLY THE CHOSEN PROJECT** while you learn the robot: the project you leave only finishes its open trades.

> **IMPORTANT** Antimartingale and Breakout use growing lots and many orders. Test every project and every new setting on a demo account first and keep the limits (max orders, max total lots, drawdown stop) inside what your account can carry.

5. The Maria Royal panel

Every project has its own panel, but the header and the project list are the same for all of them.

Header

Item	What it does
Project logo + name + small arrow	Opens or closes the project list. The name has the colour of the project's logo.
LIGHT / DARK	Light or dark theme for every panel and the chart. Chart style = Keep my chart: chart colours stay.
RIGHT > / < LEFT	Moves the panel to the right or the left side of the chart (all 8 projects).
SETTINGS > / SETTINGS <	Opens / closes the SETTINGS panel of the project (same button in all 8).
HIDE / SHOW	Folds the panel to a small strip or opens it again (the button at the bottom of the panel).
CLEAR (top-right of the chart)	Deletes old chart objects and the Maria Tools drawings. Panels and orders stay. The box next to it = Auto CLEAR.

Project list

One row per project: logo, name, magic number and state. Click a row to put that project on the panel.

State	Meaning
ON PANEL	This project is on the panel now (its row is red).
RUNNING	The project has open orders and may open new ones.
FINISHING	Not on the panel: it only finishes its open orders.
STARTED	The project on the panel is armed (for example the news grid is waiting).
ON CHART	Maria Tools has at least one tool switched on; its drawings stay on the chart while another project is on the panel.
ERROR	The project could not start with its settings. Open it and check its Inputs / SETTINGS.

Button	What it does
COMMON SETTINGS	Opens the settings every project shares (below).

RUN switch

Setting	What happens
RUN: ONLY THE CHOSEN PROJECT	Default. Only the project on the panel opens new trades.
RUN: ALL PROJECTS TOGETHER	Antimartingale, Breakout and News also trade in the background (press START on each once).

> **NOTE** Telegram, Maria AI and a Copier MASTER work only while they are on the panel.

COMMON SETTINGS

Button at the bottom of the project list. One value for every project:

Setting	Used by
Chart style	Every project: light, dark or keep my chart. The LIGHT / DARK button changes it too.
Order lines	Every project: shows the platform lines of the open orders and their SL / TP.
Slippage	Antimartingale, Breakout, Trade Manager and Copier (Maria News keeps its own slippage).
Max spread	Antimartingale, Breakout and Trade Manager: no new orders while the spread is wider.
Trading session + custom hours	Antimartingale and Breakout: when a NEW basket or grid may start.
Drawdown stop + value	Antimartingale and Breakout: when one project's own floating loss reaches the value, that project closes its orders and stops.
Referral per lot	The "Closed lots | Referral" rows of Antimartingale and Breakout.

> **TIP** The SAFETY tabs of Antimartingale and Breakout show the same shared values. Change them there or here: every project takes the new value.

SETTINGS of Trade Manager, Copier, Telegram and Maria AI

Row	How to change it
ON / OFF, lists	One click = next value.
Numbers, text	Type into the box and press Enter.
APPLY	The project starts again with the new values (saved per symbol + Magic base).

Inputs and panel values

- Every setting is also on the Inputs tab. The Strategy Tester uses only the Inputs.
- Panel values are saved per symbol + Magic base. Changed Inputs of a project win once.
- First project (Inputs) = the project on a fresh attach and in the Strategy Tester.
- Two Maria Royal robots on one symbol: give each its own Magic base.

6. Maria Antimartingale

Magic number: Magic base + 10 (2610510). Order comments: "Anti S3" (ANTI stop, side + level), "Anti CB3" (MARTIN limit copy).

What it does

Two ladders from one start price. START takes the price as the start of the cycle.

Part	What it does
ANTI ladder	STOP orders WITH the move (Anti BUY = BUY STOPs above the start, Anti SELL = SELL STOPs under it). Each next STOP = previous lot x Anti lot x.
MARTIN ladder	LIMIT copies AGAINST the move (Martin BUY = BUY LIMITs under the start, Martin SELL = SELL LIMITs above it). Each next LIMIT = previous lot x Martin lot x.
Part switches	Anti BUY, Anti SELL, Martin BUY, Martin SELL: each part ON or OFF by itself.
Anti reverse	ON: the biggest STOP is next to the start price, smaller ones further away.
Grid	Start gap, then one level every Step (pip or USD). Pending ahead = how many STOPs wait at the broker.
Follow	Ladder follow / Follow when flat: waiting orders walk after the price in full Steps.
Exit	Equity target for the whole cycle (then RESTART), optional TP / SL / trailing per order, basket trailing, loss eater.
Limits	Anti / Martin max orders, Martin lot max, Max total lots, money check before every order, drawdown stop (COMMON).

The panel

> **NOTE** SETTINGS tabs: MARTIN, EXIT and SAFETY. The shared SAFETY rows are the COMMON SETTINGS (they change for every project).

The panel has three views: the full panel (ACTIONS + LIVE), a small collapsed strip, and a SETTINGS panel that opens next to it.

Collapsed strip

Row	Meaning
Equity target (+10.00$)	The target step, the robot's profit in the current cycle and the account equity at which the target is reached (after ">").
Balance / Equity	Account balance and equity; the number in brackets is the open floating profit or loss.
BUY / SELL	Per side: how many orders are open (copies included, for example "7 open"), their lots and floating P/L.

ACTIONS

Button	What it does
START (BOTH)	Starts the robot. With GRID LOCK on, the current price becomes the start price and the grid of stops is placed for the chosen sides. With GRID LOCK off, the first order of each side opens at the market. START also clears CYCLE STOP and STOPPED.
BOTH	Use both sides: BUY STOPs above and SELL STOPs below the price.
ONLY BUY	Only the BUY side has a grid (BUY STOPs).

Button	What it does
ONLY SELL	Only the SELL side has a grid (SELL STOPs).
CYCLE STOP	Finishes the current cycle without starting a new one. Open baskets run to their end (equity target or your close); then the robot waits until you press START. The button shows STOP ARMED, then STOPPED.

> **NOTE** Changing BOTH / ONLY BUY / ONLY SELL while the robot runs takes effect at once: the stops of a side that is switched off are deleted, its open orders stay until they close.

LIVE

Row / button	Meaning
Equity target (+10.00$)	The step, the robot's profit in the current cycle and the account equity at which the target is reached (after ">").
Balance / Equity	Account balance and equity. The number in brackets is the open floating profit or loss.
Open orders	Open BUY and SELL orders of this robot, with their profit and total lots.
CLOSE ALL	Closes all open orders of this robot. The robot then stays idle until you press START.
CLOSE PROFIT	Closes only the orders that are in profit. The robot keeps running.
CLOSE LOSS	Closes only the orders that are losing. The robot keeps running.
Baskets	Shows the take profit per order setting. Each row shows a side: open grid levels / Max orders and the price of the next free grid level ("next 0.01 @ 4120.50"). A flat side shows what it waits for (opens now, off, waits session, cycle stop, stopped).
CLOSE BUY BASKET / CLOSE SELL BASKET	Closes all open orders of one side. That side places no new orders until you press START.
Spread	The current spread of the symbol.
Robot P/L (DD stop)	The robot's floating profit or loss, and the drawdown stop level when it is on.
Closed lots | Referral	Lots this robot has closed and the rebate they earned (the rebate per lot is a setting).
Status line	The last action, for example "GRID LOCK: grid fixed at 4120.25", "BUY grid level 3 filled at 4135.25", "SELL copy 0.02 lot" or "Equity target reached".

Chart lines and the CLEAR button

Next to every price where the robot has orders, a short text lists them, for example "BUY STOP 0.01 | SELL LIMIT 0.05" or "SELL 0.02 (open)". Blue = waiting orders above the price, red = waiting orders below the price, green = the level has an open order.

Troubleshooting

Problem	What to do
Nothing happens on START	AutoTrading is off or live trading is not allowed. Switch the AutoTrading button ON and tick "Allow live trading" on the robot's Common tab.
"Money guard: ... waits"	The account has not enough free margin for the next order, or the order would be too risky for the equity. Lower First lot or Lot x, or use a bigger deposit.
"Safety: max total lots reached"	Open lots of the robot reached Max total lots. Raise it or lower the lots.

Problem	What to do
A side places no more stops	Open orders plus waiting stops of that side reached Max orders, or Max total lots (open + pending) is reached. It waits for an exit.
No stop is filled for a long time	The price stays inside the Start gap around the start price. Lower Start gap, or wait for a move.
Stops are deleted and placed again	That is normal after a fill with REVERSE BY FILL or REVERSE BY PRICE (the lots of the waiting stops change) and when GRID LOCK or STOP LOTS is switched. FOLLOW moves stops without deleting them.
No new grid after a close	RESTART is OFF, CYCLE STOP is armed, or you used CLOSE ALL / CLOSE BUY BASKET / CLOSE SELL BASKET. Press START.
Levels too close or too far	Check the Step unit: USD depends on the First lot, PIP is a price distance (gold 1 pip = $0.10).
Settings come back after a restart	That is on purpose: panel values are saved per symbol and magic number. To start from the default values see the tip at the end of section 6.
Panel buttons do not react	The robot is not running on this chart. Remove it (right-click the chart → Expert list → Remove), refresh the Navigator and attach it again. The Experts tab shows the reason.
Two robots on one symbol mix up	Give each chart its own Magic base.
Strategy Tester	MT4 cannot click panel buttons in the tester. There the robot starts the baskets by itself with your settings (Strategy Tester only = true) and the values of the Inputs tab. With a very small deposit every tester order gets a safety stop loss and take profit. At the end of a test the tester closes all open orders itself.
WebRequest error 4060 / 5203	Not used by Maria Antimartingale: the robot sends no web requests.

7. Maria Breakout

Magic number: Magic base + 20 (2610520). Order comments start with "Breakout".

What it does

Maria Breakout puts BUY STOP orders above the price and SELL STOP orders below it.

When the price breaks out, the stops on that side fill one by one and ride the move.

Main features

Feature	In one line
Two-sided ladder	BUY STOPs above, SELL STOPs below. One side only is also possible.
USD distances	Start and Step are money of one zone 1 lot. The same numbers fit any symbol.
5 lot zones	Small lots near the price, bigger lots far away.
Real + virtual levels	Only zone 1 levels are real orders. The rest wait as dotted virtual lines.
Live ladder	Keeps the stops on the grid in front of the price.
HARD Max	Open trades + stops of one side never go above Max.
Trailing stop	Each trade follows its own profit.
Basket trailing	Each side (or all trades) follows its total profit.
Loss eater	Closed profit pays off a losing trade.
Equity target	At a fixed profit the robot closes all and starts a fresh ladder.

The ladder (defaults, gold, 0.01 lot)

Level	Distance	Order	Lot	Status
BUY 30	+42.00	BUY STOP	0.10	virtual (zone 5)
BUY 6	+8.40	BUY STOP	0.02	virtual (zone 2)
BUY 1 - 5	+1.40 ... +7.00	BUY STOP	0.01	real orders (zone 1)
PRICE	0	—	—	—
SELL 1 - 5	−1.40 ... −7.00	SELL STOP	0.01	real orders (zone 1)
SELL 6	−8.40	SELL STOP	0.02	virtual (zone 2)
SELL 30	−42.00	SELL STOP	0.10	virtual (zone 5)

Each side: 30 levels, 1.65 lots. Only the 5 nearest are real orders.

The panel

> **NOTE** SETTINGS tabs: GRID, EXIT and SAFETY. The shared SAFETY rows are the COMMON SETTINGS (they change for every project).

ACTIONS

Button	What it does
START	Places a new ladder at the current price.
BOTH / ONLY BUY / ONLY SELL	Picks the side.

Button	What it does
CYCLE STOP	Finishes this cycle, then waits for START.
HIDE ▲ / SHOW ▼	Folds the panel to a small strip.

LIVE

Row / button	Meaning
Equity target	Target step, profit so far, equity where it closes.
Balance / Equity	Account money. Brackets = open P/L.
Open orders	Open BUY and SELL trades, profit and lots.
CLOSE ALL / PROFIT / LOSS	Closes all, only winners or only losers.
Pending orders	Real stops + virtual levels per side.
DEL PENDING / BUY STOP / SELL STOP	Deletes stops of both sides or one side.
Spread	Current spread.
Closed lots | Referral	Closed lots and their rebate.
Status line	The last action.

CLEAR button

Removes old chart objects. Panel and orders stay.

How it works

Live ladder

Event	What the robot does
A trade closed	Its level is free again.
Price moved away	A far stop moves to a nearer level.
Empty level	The gap is filled.
Trade on a level	That level is skipped. No stacking.

HARD Max

Open BUY trades	BUY STOPs	Total (Max 5)
0	5	5
2	3	5
5	0	5

Basket trailing (each side)

Step	BUY basket	Result
Open + closed profit reaches start	+3.00	Trailing ON
Best profit	+4.20	Stop at +3.20

Step	BUY basket	Result
Profit falls to	+3.20	BUY side closes, its ladder starts again

Other symbols (Start / Step 1.40 USD, 0.01 lot)

Symbol	Price	Start / Step	Equals
XAUUSD	4100.00	1.40 USD	1.40 move
EURUSD	1.1190	1.40 USD	14 pips
USDJPY	158.70	1.40 USD	~22 pips

Troubleshooting

Problem	What to do
Nothing happens on START	Switch AutoTrading ON. Tick "Allow live trading".
Fewer stops than zone 1	Normal: Max counts open trades + stops.
No virtual lines	Turn on Virtual lines or VIRTUAL LINES on the panel.
New defaults not shown	Press Reset on the Inputs tab once.
Buttons do not react	Remove the robot and attach it again.
"price too close to market"	Increase Start distance.
"not enough money"	Use smaller lots or fewer levels.
Two robots mix up	Give each chart its own Magic base.
Strategy Tester	Buttons do not work there. Tester: auto grid places the ladder itself.

8. Maria News

Magic number: Magic base + 30 (2610530). Order comments start with "News".

What it does

Big news (Non-Farm, CPI, FOMC) makes the price jump. Nobody knows the direction.

Maria News places BUY STOP orders above the price and SELL STOP orders below it. The side the price jumps to gets filled.

You place the grid with one click (Manual), or the robot places it before each news (Auto news).

A grid: 3 stops per side, gold, Start 5, Step 5

Level	From price	Order	Note
BUY 3	+15.00	BUY STOP	farthest
BUY 2	+10.00	BUY STOP	
BUY 1	+5.00	BUY STOP	Start distance
PRICE	0	—	
SELL 1	−5.00	SELL STOP	Start distance
SELL 2	−10.00	SELL STOP	
SELL 3	−15.00	SELL STOP	farthest

Feature	In one line
Own TP + SL	Every order has its own take profit and stop loss.
Auto news	Grid placed before the news, unfilled stops cancelled after.
Protection	Spread guard, margin check, broker limits. Spike guard + OCO optional.
Own orders only	Uses only its own Magic base. Your other trades are safe.

The panel

> **NOTE** Same trading logic as the single Maria News.

Main panel

Control	What it does
MANUAL / AUTO NEWS	MANUAL: you place the grid with the buttons. AUTO NEWS: the robot places the grid by itself before the news events chosen in SETTINGS → NEWS. The line below shows the next event and the time left.
SETTINGS > (top row)	Opens the SETTINGS panel with the tabs ORDERS, EXIT and NEWS.
PLACE BUY STOP + SELL STOP	Places the whole grid at once: the buy stops above and the sell stops below the price. The x button next to it deletes all pending stops of this robot.
Next / Placed	Prices of the first buy stop and sell stop: where they would go (Next, dotted preview lines) or where they are (Placed).
BUY STOP / SELL STOP	Places only the buy side or only the sell side. Each has its own x button to delete that side.
Open trades / Pending stops	Open trades of this robot with their lots and profit, and the pending stops.

Control	What it does
CLOSE ALL	Closes the open trades and deletes the pending stops of this robot.
GRID box	Every level of the grid: BUY STOPS and SELL STOPS with their state, and a summary "Wait | Open | Done".
LIVE	Balance, equity with the floating profit, free margin, spread and the time until the candle closes.

SETTINGS panel

Tab	What you can change
ORDERS	GRID: distances in points or in price $, Start, Step, Orders per side and Lot. TP / SL for new orders: TP per order, SL per order and Total TP.
EXIT	PROTECTION of open trades: breakeven and trailing. SAFETY: spread max, spike guard, slippage, cancel time and OCO (when one side fills, the other side's stops are deleted).
NEWS	AUTO NEWS: which impact to trade, seconds before the release, max price age, hours shift, the event filter (only events with these words), tester news. NEWS ON CHART: news table ON / OFF, news lines ON / OFF and which impact to show.

The news table and the news lines are shown only while Maria News is on the panel. A grid that is already placed keeps working when you switch to another project.

How it works

When	What happens
Always	The panel shows the next news and a countdown.
60 s before	Grid placed. Spread too wide or price frozen → waits.
3 s before	Last chance. Not placed → the news is skipped.
News	One side fills. TP and SL do the work.
5 min after	Unfilled stops cancelled. Hand-placed grids stay.

> **TIP** Old stops still waiting? Auto skips the next news. Cancel them with X.

Troubleshooting

Message	Fix
"Turn on AutoTrading"	Turn the AutoTrading button ON. Tick it in the Common tab.
"allow WebRequest" (error 4060)	Add https://nfs.faireconomy.media (section 2).
"news feed: no connection"	No internet or firewall. It retries and uses the last calendar.
"Not gold: set 'Distance unit' = Points"	Set Distance unit = Points.
"Broker minimum distance is ..."	Start, TP or SL is too close. Make them bigger.
"Spread ... - not placed"	Spread too wide. Wait, or raise Max spread %.
"Margin: need ..."	Not enough margin. Lower the lot or the orders.

Message	Fix
"... already exists"	Stops are already placed. Cancel them with X first.
"Auto: event skipped - ..."	The reason is after the dash.
News times off by hours	Set Hour shift (1 or -1).

9. Maria Trade Manager

Magic number: Magic base + 40 (2610540). Order comment "Trade Manager".

What it does

A one-click trade panel for manual traders.

It draws the trade plan on the chart before you click. Then it looks after the open trade.

Tab	What it is for
TRADE	Open and close orders. Lot, SL / TP, plan on the chart.
PROTECT	Breakeven, trailing stop, TP1, daily guard, spread filter.
STATS	Results, alerts, hotkeys.

Key ideas

- **See before you click.** Entry, SL and TP zones with money and risk:reward.
- **Risk % lot.** The lot comes from the SL distance.
- **4 units for SL / TP.** Pips, money, % of balance, x ATR.
- **Drag to change.** Drag the SL, TP and entry lines on the chart.
- **Honest risk.** A stop closer than the broker allows is refused, never moved in secret.
- **Manual only.** On a live chart the panel never trades by itself.

Which trades it manages

Trades	Managed?
Opened by this panel (its Magic number)	Yes
Opened by hand (magic 0)	Yes, when Manage manual trades = true
Other robots' trades	No

The panel

> **NOTE** SETTINGS > (top of the panel) opens every setting of this project. The panel works as in the single product.

The status line at the bottom shows the last result: green = done, amber = check, red = refused.

Header and tabs

Control	What it does
Header (drag)	Move the panel. The place is remembered.
- / +	Fold or open the panel.
TRADE / PROTECT / STATS	Switch tabs.

TRADE tab - order and volume

Control	What it does
SELL / BUY	Market order with the plan's lot, SL and TP. Shift+S / Shift+B.

Control	What it does
FIXED LOT	The field is the lot.
RISK %	The field is the % of balance to risk. Needs SL ON (pips or ATR).
Order lot	Lot of the next order, rounded to the broker step.
SL / TP ON / OFF	Use a stop / target on new orders.
SL / TP value	Type the distance, press Enter.
Unit button	Pips -> money -> % -> x ATR. The price level stays the same.
Risk : Reward	TP distance / SL distance.
Spread, candle timer	Spread in pips. Time to the candle close.

TRADE tab - plan on the chart

Control	What it does
PLAN ON / OFF	Show or hide the plan (Shift+P).
SIDE: BUY / SELL	Which side the plan shows.
MARKET / PENDING	PENDING adds a dashed entry line. Drag it to your price.
PLACE PENDING	Places the pending order at the line. Limit or stop type is picked for you.
ZONES ON OPEN ORDERS	Zones with drag handles on open and pending orders.

- **Green zone** = take profit.
- The boxes show points, money, % at risk and risk:reward.
- Drag a line: the panel values follow.
- Drag a pending entry line: its SL and TP move with it.

TRADE tab - actions (this symbol)

Button	What it does
CLOSE ALL	Closes all managed positions. 2nd click within 3 s. Shift+C closes at once.
PROFIT	Closes the positions in profit.
LOSS	Closes the positions in loss. 2nd click within 3 s.
CLOSE 50%	Closes half of each position (if the lot can be split).
REVERSE	Closes one side, opens the other side with the same lot. 2nd click within 3 s.
SL TO ENTRY	SL to the entry price on positions far enough in profit.
DEL PENDING	Deletes the managed pending orders.

PROTECT tab

Control	What it does
BREAKEVEN	At "trigger" pips of profit: SL to entry + "lock" pips.
TRAILING	From "start" pips: SL follows at "distance", in "step" pips.
TP1	At "at %" of the way to TP: close "close %". Needs a TP.
AFTER TP1 -> BREAKEVEN	The rest gets SL at entry + lock.
DAILY GUARD	Daily loss / profit limit and max trades. OFF also removes today's lock.

Control	What it does
Today, Trades today, Guard	Today's result, trade count, guard state.
Max spread pips	No new orders above this spread. 0 = off.

STATS tab

Row / button	What it shows or does
THIS SYMBOL	Open positions, lots, floating P/L, closed today.
TODAY	Closed trades today (all symbols, this panel): win rate, best, worst, net.
SOUND / PUSH / POP-UP	How alerts reach you.
HOTKEYS	Shift+B buy, Shift+S sell, Shift+C close all, Shift+P plan.

How it works

Goal	Setup
Same money at risk every day	RISK % + SL unit x ATR (for example 1.5).
Lock profit early	TP1 at 50% closes 50%, Then breakeven ON. Trailing for the rest.
Prop-firm rules	DAILY GUARD ON with your firm's daily loss limit.
News days	Max spread ON.
Several panels on one symbol	A different Magic number for each one.
Breakeven + trailing together	Fine: the SL takes the better level and never moves back.

Troubleshooting

Message or problem	What to do
Buttons do nothing	AutoTrading ON + Allow live trading.
"SL under broker min X pips"	Use a larger SL (often on BTC or gold).
"Risk % mode needs SL ON"	Switch SL ON. Unit: pips or ATR.
"Min lot risks X%"	Smaller SL, bigger balance or FIXED LOT.
"Daily guard locked for today"	A limit was hit. Wait for the next server day, or switch the guard off.
"Max trades ..." / "Spread ... > max"	Change the limit on the PROTECT tab.
"Click ... again within 3 s"	Click again to confirm.
"Too fast - click again"	A double click was blocked. Click once more.
"opened WITHOUT SL/TP"	The broker refused the stops. Set SL / TP at once (drag the lines).
"Broker refused the new price"	Too close to the price (stop / freeze level). Move it further.

Message or problem	What to do
"Trailing distance under broker min"	Use a larger trailing distance.
Strategy Tester	Buttons do not work there. Only small demo trades run. Try the panel on a demo account.
Need more detail?	Experts tab (Terminal window): order errors with the broker's number. Journal tab: connection and permission messages.

10. Maria Copier

Magic number: Magic base + 50 (2610550). Order comments "Copier <key>".

What it does

Maria Copier copies trades from one MT4 account (MASTER) to other MT4 accounts (SLAVES) on the same PC or VPS.

One EA does both jobs. You pick MASTER or SLAVE in the settings.

Idea	In short
Channel	A name that links a master with its slaves (default "main").
Local file	The master writes its trades to a small file. Slaves read it. No internet, no server, no DLL.
Your lot size	SAME, MULTIPLIER, FIXED, BALANCE ratio or EQUITY ratio.
Any broker	Suffixes and other symbol names are found or mapped.
Safety first	If something looks wrong, the slave waits. It never closes copies on a guess.

What is copied

Master does	Slave does
Opens BUY / SELL	Opens a copy.
Closes	Closes the copy.
Closes a part	Closes the same part of the copy.
Moves SL / TP	Moves SL / TP of the copy.
Pending order	Copies it when it fills (or at once, if "Copy pending orders" is on).
Trade open before the slave started	Skipped (unless "Copy already open trades" is on).

> **TIP** Close a copy by hand and it is never opened again.

The panel

> **NOTE** SETTINGS > (top of the panel) opens every setting of this project. The panel works as in the single product.

A dark panel sits in the top-left corner of the chart. Drag the header to move it.

Rows

Row	Shows
Mode / Channel	MASTER or SLAVE and the channel name.
Status	The live state (see the table below).
Lots	The lot mode, for example "x1.00" or "FIXED 0.01".
Orders published	Master: how many orders it shares now.
MASTER: Account / Balance / Equity	Slave: the master it follows.

Row	Shows
Copies open / Floating P/L	Slave: its copies and their profit.
Equity guard	Slave, guard on: the equity level that fires it.
LAST ACTIONS	The last 3 actions. All actions are also in the Experts tab.

Buttons

Button	Does
PAUSE / RESUME	Stops / restarts copying (master: publishing).
SYNC NOW	Runs one copy cycle now.
CLOSE ALL COPIES	Slave: click twice in 5 s. Closes only the copies, never other trades.

Status

Status	Meaning
ONLINE	All works. "hb" = seconds since the last master signal.
WAITING FOR MASTER	No master on this channel yet.
MASTER OFFLINE	Master silent. Copies are frozen: no opens, no closes.
MASTER ACCOUNT CHANGED	Another master account appeared. Slave freezes. Re-attach to follow it.
EQUITY GUARD HIT	Guard closed all copies and paused. Press RESUME.
PAUSED	You pressed PAUSE.
NOT CONNECTED / LOADING ORDERS	Master waits for the connection and its orders.
OTHER MASTER ON CHANNEL	Another master uses this channel. Pick another name.
ALREADY ON ANOTHER CHART	This role + channel already runs on another chart.
WRITE ERROR	Master cannot write its file. See the Experts tab.
TESTER DEMO	Strategy Tester mode (see section 8).

How it works

Which lot mode?

Lot mode	Good for
SAME	Same account size, same broker.
MULTIPLIER	A fixed ratio, e.g. 0.5 for a smaller slave.
FIXED	Tests, or always the same lot.
BALANCE ratio	Lots follow the balance ratio of the two accounts.
EQUITY ratio	Like BALANCE, with open profit / loss.

> **TIP** BALANCE / EQUITY ratios convert currencies with the broker's own rates. Cent accounts (USC, EUC) = 1/100 USD / EUR.

Setups

You want	Do this
1 master, many slaves	Same channel name everywhere.
2 separate groups	Two channel names, e.g. "gold" and "fx".
2 slaves in one terminal	Different channel or magic number.
Broker uses GOLD, not XAUUSD	Symbol map: XAUUSD=GOLD.
Brokers quote a bit differently	SL / TP mode = DISTANCE.

Built-in safety

Rule	Protects you from
3 s start wait	An empty order list after a master restart.
2 snapshots to close	Closing a copy on one bad read.
Max trade age / price move	Late copies far from the master price.
Broker checks	Wrong lot step, margin, stop and freeze levels.

Troubleshooting

Problem	Fix
WAITING FOR MASTER	Master not on this PC, or channel names differ.
MASTER OFFLINE	Master terminal closed, offline or paused.
ONLINE but nothing copied	AutoTrading ON? Filters? Max open copies? Trade older than the slave?
"symbol ... not found"	Add a Symbol map entry or slave prefix / suffix.
"older than 300 s"	Raise Max trade age, or 0 = off.
"not enough free margin"	Lower the multiplier or Max lot.
OTHER MASTER ON CHANNEL	Give one master another channel name.
ALREADY ON ANOTHER CHART	Remove the second EA, or use another channel / magic.
No push messages	Set your MetaQuotes ID in Tools → Options → Notifications.

11. Maria Telegram

Magic number: Magic base + 60 (2610560), used only by the Strategy Tester demo. Maria Telegram sends messages; it does not open trades on a live chart.

What it does

Maria Telegram sends your MetaTrader 4 account to your phone.

It only reads the account. It never opens, changes or closes a trade.

Message	When
DAILY REPORT	Every day at your report time.
SCHEDULED REPORT	Every N minutes (if you turn it on).
WEEKLY SUMMARY	Friday at the report time.
MONTHLY SUMMARY	Last day of the month.
TRADE OPENED	A trade opens: price, SL, TP, risk.
TRADE CLOSED	A trade closes: result, pips, time.
DRAWDOWN ALERT	Floating loss reaches your %.
LOW MARGIN ALERT	Margin level falls below your %.
Chart picture	With reports, closes, or on /chart.

A report shows balance, equity, margin, floating P/L, drawdown, today / week / month results and open trades.

The panel

> **NOTE** SETTINGS > (top of the panel) opens every setting of this project. The panel works as in the single product.

The panel sits in the top-left corner. Drag the header to move it.

BOT

Row	Meaning
Status	Ready = all good. Not configured = token or chat ID missing. Paused = wrong token or chat ID (fix, then SEND TEST). Standby = another chart sends.
Queue	Messages waiting to be sent.
Last sent	Time of the last message (PC time).
Next report	Time and type of the next report.
Commands	On = chat commands work.

ACCOUNT

Row	Meaning
Today closed P/L	Result of trades closed today.
Floating P/L	Profit or loss of open trades.
Drawdown float / max	Open loss in % / biggest drop in history.
Equity	Account equity now.

Buttons

Button	What it does
SEND STATS	Sends the full report now.
SEND CHART	Sends a picture of this chart.
POSITIONS	Sends the open trades.
SEND TEST	Sends "TEST OK". Also restarts sending after a pause.

Telegram commands

Command	What you get
/stats	Full account report.
/chart	Picture of the robot's chart.
/chart EURUSD H1	Any symbol and timeframe. Also /chart H4, /chart GOLD M15, /chart eurusd.
/positions	Open trades.
/today	Trades closed today.
/help	List of commands.

Only your chat ID gets answers. Commands older than 3 minutes are skipped.

> **TIP** /chart uses an open chart with your indicators. If none is open, the robot opens one for a few seconds.

How it works

Topic	Answer
How many copies?	One copy on any chart covers the whole account.
Copy on two charts?	Only one sends. The other shows "Standby".
Own bot	Give Maria Telegram its own bot. Two programs on one bot steal commands.
Public channel	Turn on Privacy mode. Results show in %.
Grids and baskets	Trades at the same moment come in one message.
Report time	Broker server time (chart time).
Quiet hours	Your PC time.
Alerts	Always ring, also in quiet hours.
MT4 restart	Restart within 3 hours after the report time: the report is sent "late".
Statistics	From the loaded history. Account History tab → right-click → All History.

Troubleshooting

Problem	Fix
Not configured	Enter bot token and chat ID.
Error 4060 / "Allow https://api.telegram.org"	Add the address in Tools → Options → Expert Advisors.

Problem	Fix
Error 5203 / no connection	Check internet, firewall or VPN.
Paused: "Unauthorized"	Wrong token. Copy it again, press SEND TEST.
Paused: "chat not found"	Wrong chat ID, or the bot is not in the chat. Fix it, press SEND TEST.
"Off: webhook / other app"	Another program uses this bot. Make a new bot.
No answer to commands	Command must come from your chat ID. "Chat commands" = true.
/chart: "Symbol not found"	Use the name from Market Watch, e.g. /chart EURUSD.m H1.
"chart screenshot was not ready"	Do not minimise the chart window.
Week / month numbers too small	Account History → All History.
AutoTrading is off	Fine: the robot does not trade.
Nothing sent in the tester	Normal. The tester blocks web requests.

12. Maria AI

Magic number: Magic base + 70 (2610570); trade ideas placed from the AI card use base + 71 (2610571) and the comment "AI idea".

What it does

Maria AI is an AI market analyst in your MetaTrader 4 chart.

You ask in plain words. The AI answers in the chart in a few seconds.

It uses live data from your broker, fresh news and the economic calendar. It never guesses prices.

Feature	What you get
Market chat	Ask about any market: "what is happening on gold?"
Levels	Support and resistance lines drawn on the chart.
Trade check	CHECK BUY / CHECK SELL: GO, CAUTION or WAIT with reasons.
Trade idea	Entry, SL and TP. Press PLACE to open it (with a confirm).
Price alerts	Type "alert gold above 2400".
Brief + scan	Morning brief and a watchlist scan.
News	Reminder before the news and an explainer after it.
Telegram	Chat with Maria AI from your phone.
Trade coach	Every closed trade gets a grade 0-100 and a tip.

> **TIP** Maria AI never trades by itself. An order opens only after you press PLACE and confirm.

A question about gold: answer, levels and a BUY idea.

The panel

> **NOTE** SETTINGS > (top of the panel) opens every setting of this project. The panel works as in the single product.

Two tabs: MARKET CHAT for questions and tools, TRADE COACH for your closed trades.

MARKET CHAT: the same panel in English and in Spanish.

Top buttons

Button	What it does
AI: <name>	Switches to the next AI that has a key.
LEVELS	Shows or hides the level lines.
CHART PIC	Sends the AI a picture of this chart.
CLEAR	Clears the chat, its memory and the levels.
- / +	Folds or opens the panel.

Answer symbols

Symbol	Meaning
Green up triangle	Bullish

Symbol	Meaning
Red down triangle	Bearish
Dot	Fact or level
Amber !	Risk
Hourglass	Coming event
Orange arrow	What to watch

Scroll: drag the text up or down, or drag the scroll bar. The arrows move 5 rows.

Tools

Button	What it does
THIS CHART	What is happening on this symbol now?
GOLD	The same question about gold.
NEWS TODAY	Today's news and how it can move this symbol.
CHECK BUY / SELL	Checks a trade before you enter: GO, CAUTION or WAIT.
TRADE IDEA	A trade with entry, SL and TP, drawn on the chart.
BRIEF	Morning brief for your watchlist.
SCAN	Ranks the watchlist by trend. The AI picks the best.
Text box + SEND	Any question. About 63 characters (an MT4 limit).
RESET LIMIT	Sets today's AI counter back to 0.

Trade idea card

Button	What it does
PLACE	Opens the order after a confirm. The lot risks PLACE risk % of your balance.
DISMISS	Removes the card and its zones.

A SELL idea: TP / SL zones with money, and PLACE.

TRADE COACH tab

Row / button	What it shows
LAST TRADE	Last closed trade, result and grade (0-100).
FEEDBACK	The coach's tip for that trade.
TODAY	Trades, wins, mistakes, average grade.
REVIEW LAST	Reviews the last trade again.
WEEK REPORT	The week's coaching report.
JOURNAL	Shows where the journal file is.

How it works

Topic	In short
What the AI gets	Live M15 / H1 / H4 / D1 data, news, calendar, last answers, chart picture.

Topic	In short
Symbols	Words like gold, euro, oil, bitcoin work. Up to 3 per question.
Levels	From the answer. If none: the chart's own swing levels.
Trade check	Offline rules first. With a key the AI adds GO / CAUTION / WAIT.
PLACE guard	Refused if the price already passed the SL or the TP is wrong.
Several charts	One chart is the master: Telegram, alerts, trade check. Nothing twice.
Without a key	Coach, price alerts, CHECK and SCAN still work offline.
Strategy Tester	No internet there. Only the offline coach and demo trades.

TIP Use a cheap model (Haiku, Luna, DeepSeek Flash) every day. Use a strong one for big decisions.

Troubleshooting

Problem	Fix
"No API key"	Paste a key, or press the AI button.
Error 4060 / URL not allowed	Add the address in Options (section 2).
Error 5203 / no connection	Check internet, firewall or VPN. It retries.
HTTP 401 / 403	Key wrong, expired or no credit.
Daily limit reached	Press RESET LIMIT or raise the limit.
No levels	LEVELS on? Was the question about this symbol?
PLACE does nothing	AutoTrading ON + Allow live trading.
Mouse wheel does not scroll	MT4 does not send it. Drag the text instead.

13. Maria Tools

Maria Tools draws analysis on the chart. It never trades. Its drawings stay while another project is on the panel.

What it does

Tool	What you see on the chart
MA	A fast and a slow moving average (SMA, EMA, SMMA or LWMA), drawn over the last bars.
BANDS	Bollinger Bands: middle line and two bands.
FIBO	Automatic Fibonacci of the last swing, with extensions and price tags.
PIVOTS	Daily, weekly or monthly pivots: Classic, Fibonacci, Camarilla or Woodie, with previous high / low.
SESSIONS	Asia, London and New York boxes (GMT hours with summer time), outline or filled, with the range or the high / low prices.
S/R ZONES	Support and resistance zones from swing clusters, strongest first.
OSC	Oscillator block on the panel: RSI, MACD histogram, ATR in pips, Stochastic, a BULL / BEAR / MIXED bias and the M15 / H1 / H4 / D1 trend arrows.
SUPPLY / DEMAND	Supply and demand zones with their strength (weak, untested, verified, proven) and retests; flipped (turncoat) zones in their own colour.
NEURAL	A forecast line past the last bar from a sine-wave (harmonic) fit of the past prices. The panel shows "up to ... in N bars".
ELLIOTT	Swing pivots with wave labels (1-2-3-4-5-A-B-C), the zigzag, a Fibonacci on the last leg, target levels and the base trend line.
CLUSTER	A volume cluster (footprint style) view of the newest bars with the point of control and a volume profile. The cells are an estimate built from the M1 tick volume inside each bar (MetaTrader gives no real bid / ask volume to a robot).
ALERTS	Alerts when the price touches a pivot, Fibonacci, S/R or supply / demand level, and on a closed-bar MA cross. Optional push to the phone.

The panel

Control	What it does
CHART TOOLS	One button per tool, with a small icon and a one-line read-out under it. Click to switch the tool ON or OFF.
PRESETS	SCALPER, INTRADAY, SWING and CLEAN switch a ready set of the indicator tools on (with their MA periods). CLEAN switches everything off.
LOAD ALL / CLEAR ALL	Switches every tool on / off. The CLEAR button of Antimartingale and Breakout also switches every tool off.
SETTINGS > (top row)	Opens the SETTINGS panel with the tabs LINES, LEVELS, SESSIONS, ZONES, ANALYSIS and OSC + ALERTS. Type a value and press Enter; colours as R,G,B. Saved per symbol.
OSCILLATORS block	Shown while OSC is ON: RSI, MACD, ATR, Stochastic, bias and trend arrows of the chart timeframe.
Status line	Tools on, MA periods, spread and the time until the bar closes.

How the features work together

> **TIP** Heavy tools (SUPPLY / DEMAND, ELLIOTT, CLUSTER) are calculated on a new bar, not on every tick, so they do not slow the trading projects down.

14. Tips: using the projects together

Good combinations

- **Trade + tools.** Switch on the Maria Tools you like (sessions, pivots, supply / demand), then put Antimartingale, Breakout or Trade Manager on the panel. The drawings stay.
- **Robot + manual trades.** Trade Manager manages its own trades (magic base + 40). Antimartingale and Breakout never touch them, and Trade Manager does not touch the robot baskets.
- **Reports.** Put Maria Telegram on the panel on a separate chart of the same terminal if you want messages all day while you work with another project on this chart. Give that chart its own Magic base.
- **Before news.** Maria News on the panel shows the calendar table; Maria AI can remind you of the news and explain the release afterwards.

Magic numbers and several charts

Two charts of the same symbol: change the Magic base on one of them (for example 2610600). Different symbols never mix.

Strategy Tester

Pick the project with "First project". "Tester demo trades" = true: it trades by itself with its Inputs. Only that project runs. No internet in the tester (Telegram, AI, live news calendar).


Updating and saved values

After an update with new defaults: press Reset on the Inputs tab, then OK.

15. Settings reference

410 settings, in the order of the Inputs tab: MAIN, COMMON, then one block per project ("ANTIMARTINGALE SETTINGS", ...). Sub-values are indented under their switch.

MAIN SETTINGS



Inputs window: MAIN SETTINGS + COMMON.


Setting	Default	What it does
polymaria.net"; // Website	https://polymaria.net	Polymaria.net
t.me/polymaria_net"; // Telegram	https://t.me/polymaria_net	Telegram channel
Magic base	2610500	Antimartingale +10, Breakout +20, News +30, Trade Manager +40, Copier +50, Telegram +60, AI +70 (+71 ideas)
Tester demo trades	true	The chosen project trades by itself (demo). Live charts ignore this
First project	Antimartingale	On attach / inputs change and in the Strategy Tester

COMMON SETTINGS

Setting	Default	What it does
Chart style	Dark	Light / dark / keep my chart (Antimartingale, Breakout)
Show order lines	true	Show order lines (SL / TP levels) on the chart
Slippage (points)	30	Slippage, points (Antimartingale, Breakout, Trade Manager, Copier)
Max spread (pips)	0.0	No new orders while wider (0 = no limit) (Antimartingale, Breakout, Trade Manager)

Setting	Default	What it does
Session	Any time	Trading session for NEW baskets / grids (Antimartingale, Breakout)
From (HH:MM)	08:00	From (server time, HH:MM)
To (HH:MM)	20:00	To (server time, HH:MM)
Drawdown stop	OFF	OFF / $ / % of balance (each project: its own floating loss -> close it + STOP)
DD value	30.0	Drawdown stop value
Rebate per lot	7.0	Referral / rebate per 1.00 lot closed (account money)

ANTIMARTINGALE SETTINGS



Inputs window: ANTIMARTINGALE SETTINGS.

MARTIN

Setting	Default	What it does
Martin BUY (BUY LIMIT under the start)	true	Martin BUY (BUY LIMIT under the start)
Martin SELL (SELL LIMIT above the start)	false	Martin SELL (SELL LIMIT above the start)
Martin ON / OFF	ON	Classic / Copy (each martingale order is mirrored on the other side) / Bank
Martin first lot	0.01	Martin first lot
Martin lot x	1.20	Martin lot x
Martin max orders	15	Martin max orders
Martin lot max (0 = no limit)	0.50	Martin lot max (0 = no limit)

ANTIMARTIN


Setting	Default	What it does
Anti BUY (BUY STOP above the start)	false	Anti BUY (BUY STOP above the start)
Anti SELL (SELL STOP under the start)	true	Anti SELL (SELL STOP under the start)
Anti first lot	0.01	Anti first lot
Anti lot x	1.20	Each next order = previous lot x this (2 = double)
Anti max orders	10	Max orders per side (HARD limit, first order = 1)
Anti reverse (biggest next to start)	true	Anti reverse (biggest next to start)
Anti pending ahead	10	How many next levels wait at the broker (1-50)

GRID + EXIT

Setting	Default	What it does
Ladder follow	false	The pending ladder walks after the price in full Steps (never back)
Start gap (Steps)	2.0	Distance from the cycle start price (and, with FOLLOW)
Step unit	USD	Pip / USD (USD = the distance over which the first lot makes this many dollars)
Step	5.0	Distance from the last order to the next order (in the Step unit above)
One fill per level	false	One fill per level
Auto merge (equal lots)	true	Auto merge (equal lots)
Follow price when flat (no open order)	true	Follow price when flat (no open order)
Equity target counts	All together	All trades together / each side alone
Equity target	$	OFF / $ / % of balance / = Step money
Equity target value	50.0	Robot's own profit -> close all, fresh start (each cycle counts from zero)
Take profit	OFF	OFF / % / pip / USD money (USD = each order closes at this profit, any lot)
TP value	50.0	Take profit value
Stop loss	OFF	OFF / % / pip / USD money
SL value	5.00	Stop loss value
Trailing stop	OFF	OFF / % / pip / USD money
Trailing start	1.00	Profit distance before trailing begins
Trailing unit	USD	% / pip / USD money
Trailing distance	0.50	SL follows price at this distance
Basket trailing	OFF	OFF / all trades together / each side alone (trails the open profit of the basket)
Basket trailing start	5.0	Open profit of the basket (account money) before trailing begins

Setting	Default	What it does
Basket trailing distance	3.0	The basket closes when it falls this much from its best
Restart after close	true	The next first order opens again (panel RESTART switch)
Loss eater	OFF	OFF / smallest / biggest loss first (closed profit pays a losing order)
Loss eater min ($)	10.0	Only orders losing more than this (account money)
Max total lots	500.00	Open lots of this robot, both sides (0 = no limit)
Panel on the right	false	Panel on the RIGHT side of the chart (panel pill switches it)
Panel: collapse on start	true	Collapse on start
Panel: settings open	false	Settings panel open on attach (SETTINGS button opens it)
Show trade arrows	false	Show order open/close arrows on the chart
Show next level line	true	Show the next martingale level as a dotted line
Auto clear (candles, -1 = off)	0	Delete chart objects every N new candles (0 = always, at once)

BREAKOUT SETTINGS



Inputs window: BREAKOUT SETTINGS.

GRID

Setting	Default	What it does
Side	BOTH	Both / only BUY / only SELL (START, restart and re-arm use it)
Start / Step unit	USD	USD (money per Zone 1 lot, any symbol) / % / pip
Start distance	1.40	Start distance from price (unit above)

Setting	Default	What it does
Step	1.40	Step between levels (unit above)

LOT

Setting	Default	What it does
Zone 1 lot	0.01	Zone 1 lot (nearest levels)
Zone 1 levels	5	Zone 1 levels (= real pending orders per side)
Zone 2 lot	0.02	Zone 2 lot
Zone 2 levels	5	Zone 2 levels
Zone 3 lot	0.04	Zone 3 lot
Zone 3 levels	5	Zone 3 levels
Zone 4 lot	0.06	Zone 4 lot
Zone 4 levels	5	Zone 4 levels (0 = off)
Zone 5 lot	0.10	Zone 5 lot (farthest levels)
Zone 5 levels	10	Zone 5 levels (0 = off)

LADDER

Setting	Default	What it does
Live ladder	true	Each side always keeps its levels on the grid ahead of the price (re-arm + trail + fill gaps in one)
Max BUY (0 = off)	5	HARD limit - open BUY trades + BUY stops never more than this (0 = no limit)
Max SELL (0 = off)	5	HARD limit - open SELL trades + SELL stops never more than this (0 = no limit)

TRAILING

Setting	Default	What it does
Trailing stop	USD	OFF / % / pip / USD money
Trail start	1.00	Profit distance before trailing begins
Trail distance unit	USD	% / pip / USD money
Trail distance	0.50	SL follows price at this distance
Basket trailing	Each side	OFF / all trades together / each side alone (trails the open profit of the basket)
Basket start $	3.0	Open profit of the basket (account money) before trailing begins
Basket distance $	1.0	The basket (open + closed since it started trailing) closes when it falls this much from its best


LOSS EATER

Setting	Default	What it does
Loss eater	Smallest first	OFF / smallest loss first / biggest loss first (closed profit pays a losing trade)
Min loss $	2.0	Only trades losing more than this (account money)

EXIT + SAFETY

Setting	Default	What it does
Equity counts	All together	All trades together / each side alone
Equity target	$	OFF / $ / % of balance / = Start distance
Target value	2.0	Robot's own profit -> close all, fresh grid (manual trades not counted)
Take profit	OFF	OFF / % / pip / USD money
TP value	5.00	Take profit value
Stop loss	OFF	OFF / % / pip / USD money
SL value	5.00	Stop loss value
Off-session: delete stops	false	Remove pending stops (they come back in the session)
Max lots (0 = off)	0.0	Open + pending lots of this robot (0 = no limit)
Virtual lines	true	Show virtual levels (dotted lines) on the chart
Auto CLEAR (-1 = off)	0	Delete chart objects every N new candles (0 = always, at once)

NEWS SETTINGS



Inputs window: NEWS SETTINGS.

GRID

Setting	Default	What it does
Mode	Manual (panel)	Mode (also switchable on the panel)
Distance unit	Price ($)	Distances are in
Lot size	0.01	Lot size
Orders per side (1-20)	1	Stop orders per side (1-20)
First stop distance	5.0	First stop distance from price
Step between stops	5.0	Step between stops

EXIT + SAFETY

Setting	Default	What it does
Take profit	true	Take profit on new orders
TP distance	20.0	Take profit from entry
Stop loss	true	Stop loss on new orders
SL distance	10.0	Stop loss from entry
Trailing stop	false	Trailing stop on open positions
Trailing distance	5.0	Trailing distance (starts once profit reaches it)
Breakeven	false	Breakeven on open positions
Breakeven after	5.0	Move SL to entry after this price move
Total profit close	false	Close everything at a money target
Total profit (money)	10.0	Floating profit of all trades, account money
Max spread % (0 = off)	30.0	Max spread, % of the first stop distance (0 = off)
Spike guard	false	Close a fill that slipped too far past its stop
Max slippage %	50.0	Max slippage, % of the first stop distance
OCO (cancel other side)	false	Cancel the other side's stops when one side fills
Close slippage (points)	100	Max slippage when closing, points

AUTO NEWS

Setting	Default	What it does
News to trade	High only	Which news to trade
Place before (sec)	60	Seconds before the event to place the grid
Cancel after (min, 0 = never)	5	Minutes after the event to cancel unfilled stops (0 = never)
Event keywords	Non-Farm,CPI,FOMC,Federal Funds Rate,Unemployment Rate,GDP,Retail Sales,PCE	Only events whose name contains one of these (comma list, empty = all)
Max price age (sec)	10	Skip while the last price is older than N sec (0 = off)

Setting	Default	What it does
Test event in (min, demo)	0	Fake high USD event in N minutes (0 = off, demo only)


NEWS TABLE

Setting	Default	What it does
News table	true	News table on chart (Forex Factory)
Table news	All news	Which news to show
Event lines	true	Dotted vertical line at each event
Hour shift	0	Extra hours shift (feed is auto-shifted to server time)

TESTER

Setting	Default	What it does
Tester news every (h)	4	Strategy Tester only (no live calendar there): simulated news every N hours, grid placed before it

TRADE MANAGER SETTINGS



Inputs window: TRADE MANAGER SETTINGS.

ORDER

Setting	Default	What it does
Manage manual trades	true	Manage manual trades too (magic 0)
Order comment	Trade Manager	Order comment

LOT

Setting	Default	What it does
Lot mode	Fixed lot	Lot mode (start value, switch on the panel)
Fixed lot	0.01	Fixed lot
Risk %	1.0	Risk % of balance per trade (needs SL ON)

SL / TP

Setting	Default	What it does
Stop loss	true	Use stop loss
SL value	20.0	Stop loss value
SL unit	Pips	Stop loss unit (switch on the panel)
Take profit	true	Use take profit
TP value	40.0	Take profit value
TP unit	Pips	Take profit unit (switch on the panel)
ATR period	14	ATR period for the "x ATR" unit (current timeframe, last closed bar)

PLAN

Setting	Default	What it does
Trade plan	true	Show the trade plan (entry / SL / TP zones) before you click
Pending gap (pips)	20.0	New pending line starts this many pips away from price
Hide when in trade	true	Hide the market plan while a position is open on this symbol

BREAKEVEN

Setting	Default	What it does
Breakeven	false	Breakeven ON at start
Trigger (pips)	15.0	Move SL when profit reaches (pips)
Lock (pips)	2.0	Lock this many pips beyond entry

TRAILING

Setting	Default	What it does
Trailing stop	false	Trailing stop ON at start
Start (pips)	20.0	Start when profit reaches (pips)
Distance (pips)	15.0	Keep SL this far from price (pips)
Step (pips)	5.0	Move SL only in steps of (pips)

TP1

Setting	Default	What it does
Partial TP (TP1)	false	Partial TP ON at start (needs a TP on the order)
At % of TP	50.0	TP1 fires at this % of the way from entry to TP
Close %	50.0	TP1 closes this % of the position
Then breakeven	true	After TP1 move SL to breakeven (+ breakeven lock pips)

DAILY GUARD

Setting	Default	What it does
Daily guard	false	Daily guard ON at start
Max loss (0 = off)	5.0	Max daily loss (closed + floating, 0 = off)
Loss unit	% day balance	Max daily loss unit
Profit target (0 = off)	0.0	Daily profit target - close all and stop for the day (0 = off)
Profit unit	% day balance	Daily profit target unit
Max trades/day (0 = off)	0	Max new trades per day from this panel (0 = off)
On limit close	Panel orders	When a limit is hit, close


OTHER

Setting	Default	What it does
Sound alert	true	Sound when TP / SL / TP1 hits or the guard locks
Push alert	false	Phone push notification (set MetaQuotes ID in Options)
Pop-up alert	false	Pop-up alert window
Hotkeys	true	Shift+B buy, Shift+S sell, Shift+C close all, Shift+P plan
Order zones	true	Show zones for open + pending orders (drag a line to move entry / TP / SL)
Confirm close	true	CLOSE ALL / LOSS / REVERSE need a second click within 3 s

TESTER

Setting	Default	What it does
Every N bars	50	Open a minimum-lot trade on the first bar, then every N bars
Hold N bars	10	SL to entry halfway if in profit, close after N bars

COPIER SETTINGS



Inputs window: COPIER SETTINGS.

COPIER

Setting	Default	What it does
Mode	MASTER	MASTER publishes trades, SLAVE copies them
Channel name	main	Channel name (must be the same on master and slave)
Speed (ms)	250	Timer in milliseconds (write / read interval, min 50)

MASTER

Setting	Default	What it does
Only these symbols	(empty)	Symbols to publish, comma list (empty = all)
Only this magic (-1 = all)	-1	Publish only orders with this magic (-1 = all)

SLAVE

Setting	Default	What it does
Master offline after (sec)	10	Master OFFLINE when heartbeat older than (seconds) - no new copies, no closes
Copy already open trades	false	Also copy market orders that already existed when the slave started
Copy pending orders	false	Copy pending orders too (false = copy them when they fill)
Copy SL / TP	true	Copy SL/TP (on open and when the master changes them)
SL / TP mode	PRICE	SL/TP mode (DISTANCE = brokers with different quotes)

Setting	Default	What it does
Reverse copy	false	Reverse copy (BUY<->SELL, SL<->TP)
Max price move (0 = off)	0	Skip a new copy when price moved this many points against it (0 = off)
Max trade age sec (0 = off)	300	Never copy master orders older than (seconds, 0 = off)

LOT

Setting	Default	What it does
Lot mode	MULTIPLIER	Lot mode
Multiplier	1.0	Lot multiplier (MULTIPLIER, BALANCE and EQUITY modes)
Fixed lot	0.01	Fixed lot (FIXED mode)
Max lot (0 = no cap)	5.0	Max lot per copy (0 = no cap)
Raise to min lot	true	True = raise to minimum, false = skip the copy
Adjust contract size	true	Adjust lots when contract sizes differ (e.g. gold 100 oz vs 10 oz)
Max open copies (0 = off)	50	Max open copies (0 = no limit)


SYMBOL

Setting	Default	What it does
Remove master suffix	(empty)	Strip this suffix from master symbols (e.g. .m)
Add slave prefix	(empty)	Add this prefix to slave symbols
Add slave suffix	(empty)	Add this suffix to slave symbols
Auto find symbol	true	Find the slave symbol automatically (EURUSD -> EURUSDm, EURUSD.pro)
Symbol map (A=B,C=D)	(empty)	Symbol map master=slave, comma list (e.g. XAUUSD=GOLD,US30=DJ30)
Copy only symbols	(empty)	Copy only these master symbols, comma list (empty = all)
Never copy symbols	(empty)	Never copy these master symbols, comma list
Copy only magics	(empty)	Copy only these master magic numbers, comma list (empty = all)

OTHER

Setting	Default	What it does
Equity guard % (0 = off)	0.0	Close all copies + pause when equity falls this % below its peak (0 = off)
Close if master off (min)	0	Close all copies when the master is offline this many minutes (0 = off)
Pop-up alerts	false	Pop-up alert on important events
Phone push alerts	true	Push to phone (set MetaQuotes ID in Tools > Options > Notifications)

TELEGRAM SETTINGS



Inputs window: TELEGRAM SETTINGS.

TELEGRAM

Setting	Default	What it does
Bot token (empty = saved)	(empty)	Bot token from @BotFather (empty = saved one, - = forget)
Chat ID (empty = saved)	(empty)	User, group or @channel (empty = saved one, - = forget)
Remember on this PC	true	Remember token + chat ID on this PC (encrypted)
Account label	(empty)	Account label shown in every message (empty = none)
Chat commands	true	Answer /stats /chart /positions /today /help (your chat only)
Check every, sec	5	Check for commands every N seconds (3-60)

REPORT

Setting	Default	What it does
Report every, min (0 = off)	0	Stats report every N minutes (0 = off)
Daily report	true	Daily stats report on
Report time (server)	23:55	Daily / weekly / monthly report time HH:MM (server time)
Skip weekends	true	No daily report on Saturday and Sunday
Weekly summary (Friday)	true	Weekly summary on Friday at the report time
Monthly summary	true	Monthly summary on the last day of the month
Chart with reports	false	Attach this chart's screenshot to scheduled reports

TRADE

Setting	Default	What it does
Trade opened card	true	Message when a trade opens
Trade closed card	true	Message when a trade closes (with result)
Chart with closes	false	Attach this chart's screenshot to trade-close messages
Group trades, sec	3	Trades opened/closed within N seconds go in one message (0 = one each)
Magic filter (-1 = all)	-1	Magic number (-1 = all trades)
Open trades listed	10	Open positions listed in a report (0-20)

ALERT

Setting	Default	What it does
Drawdown alert, % (0 = off)	10.0	Alert when floating loss reaches N % of balance (again at 2N, 3N)
Margin level alert, % (0 = off)	200.0	Alert when margin level falls below N % (0 = off)

PRIVACY

Setting	Default	What it does
Privacy mode (show %)	false	Hide account, lots and money (show %)
Quiet from (PC time)	(empty)	Quiet hours from HH:MM, PC time (empty = off)
Quiet until	(empty)	Quiet hours until HH:MM, PC time


PICTURE

Setting	Default	What it does
Picture width, px	1280	Screenshot width, pixels
Picture height, px	720	Screenshot height, pixels

SENDING

Setting	Default	What it does
Retries	3	Retries per message after a failure
First retry, sec	5	First retry delay, seconds (doubles each retry)
Queue size	30	Max messages waiting in the queue (oldest dropped)

AI SETTINGS



Inputs window: AI SETTINGS.

AI

Setting	Default	What it does
AI provider	Claude	AI provider at start
Claude API key	(empty)	Anthropic Claude API key
Claude model	Opus 5.5 (recommended)	Claude model
Claude custom id	(empty)	Claude custom model id (Model = Custom)
OpenAI API key	(empty)	OpenAI API key
OpenAI model	GPT-6 Astra (smartest)	OpenAI model
OpenAI custom id	(empty)	OpenAI custom model id (Model = Custom)
DeepSeek API key	(empty)	DeepSeek API key
DeepSeek model	Flash (reads pictures)	DeepSeek model
DeepSeek custom id	(empty)	DeepSeek custom model id (Model = Custom)
Remember keys on this PC	true	Remember keys + Telegram on this PC (encrypted)
Answer language	English	Answer language
Other language	(empty)	Other language name (Language = Other)

CHAT

Setting	Default	What it does
Web search	true	Claude / OpenAI may search the web for the latest news

Setting	Default	What it does
News headlines	true	Add Google News headlines to every question (all providers)
Chart picture	true	Show the AI a picture of this chart (Claude / OpenAI)
Draw levels	true	Draw the AI's support / resistance levels on this chart
Answer timeout (sec)	90	Max wait for an answer (seconds)

TRADE CHECK

Setting	Default	What it does
Check new trades	true	Check every trade you open (news, trend, risk) and warn
Warning pop-up	true	Pop-up when a warning is found
Ask the AI too	false	Also ask the AI about each new trade (uses requests)
News window (min)	30	Warn when news (minimum impact) is within N minutes
PLACE risk %	1.0	Risk per trade, % of balance

BRIEF + SCAN

Setting	Default	What it does
Watchlist	EURUSD,GBPUSD,USDJPY,XAUUSD,BTCUSD	Watchlist (comma separated, words like gold / bitcoin work)
Brief time (empty = off)	08:00	Morning brief time, server time HH:MM (empty = off)
Brief on weekend	false	Morning brief also on Saturday and Sunday

NEWS

Setting	Default	What it does
News reminder	true	Remind before economic news
Min impact (1-3)	3	1 = low, 2 = medium, 3 = high
Minutes before	15	Remind this many minutes before the release
All currencies	false	All currencies (false = only the chart symbol's currencies)
Sound	true	Sound
Pop-up	true	Pop-up alert
Phone push	false	Phone push (MetaQuotes ID in Options)
After-news explainer	true	Explain news after the release (actual vs forecast, price move)
Minutes after	3	Explain this many minutes after the release

PRICE ALERT

Setting	Default	What it does
Alert sound	true	Sound
Alert pop-up	true	Pop-up
Alert phone push	false	Phone push (MetaQuotes ID in Options)

TELEGRAM

Setting	Default	What it does
Bot token	(empty)	Telegram bot token (from @BotFather)
Chat ID	(empty)	Your Telegram chat ID (only this chat may ask)
Answer questions	true	Answer questions sent to the bot
Send alerts	true	Send price alerts and trade check warnings to Telegram
Send brief + reports	true	Send the morning brief, news explainer and week report to Telegram

COACH

Setting	Default	What it does
All symbols	true	Review trades of all symbols (false = this chart symbol only)
Magic filter (-1 = all)	-1	Magic number filter (-1 = all trades, 0 = manual only)
AI reviews losers only	false	AI review only losing trades (offline coach still reviews all)
Max risk %	2.0	Max risk per trade, % of balance at entry
Revenge window (min)	15	Opened within N minutes after a losing close
Max trades / day	5	More than N trades opened in one day
Loser hold x	2.0	Loser held more than X times the average winner hold time
Min reward:risk (0 = off)	1.0	Planned reward:risk below this is a mistake (0 = off)
Friday week report	true	Write the week report every Friday after the time below
Report time	21:00	Friday report time, server time HH:MM


GRADE PENALTY

Setting	Default	What it does
No stop loss	35	No stop loss
Risk too big	25	Risk above max %
Revenge trade	20	Revenge trade
Overtrading	10	Overtrading
Loser held long	15	Loser held too long
Poor reward:risk	10	Planned R:R below minimum

OTHER

Setting	Default	What it does
Max AI requests / day	50	Max AI requests per day, chat + reviews (cost control)

TOOLS SETTINGS



Inputs window: TOOLS SETTINGS.

TOOLS AT START

Setting	Default	What it does
MA	false	MA on at start
BANDS	false	BANDS on at start
FIBO	false	FIBO on at start
PIVOTS	false	PIVOTS on at start
SESSIONS	false	SESSIONS on at start
S/R ZONES	false	S/R ZONES on at start
OSC block	true	OSC block on at start
SUPPLY / DEMAND	false	SUPPLY / DEMAND on at start
NEURAL	false	NEURAL forecast on at start
ELLIOTT	false	ELLIOTT waves on at start
CLUSTER	false	CLUSTER view on at start
Line bars	300	Last N bars drawn
Label size	8	Chart label font size

MA

Setting	Default	What it does
Fast MA	20	Fast MA period
Slow MA	50	Slow MA period
MA method	Exponential	MA method
MA price	Close price	MA applied price
Fast MA colour	DodgerBlue	Fast MA colour
Slow MA colour	Orange	Slow MA colour
MA width	2	MA line width
Scalper fast MA	9	Fast MA period
Scalper slow MA	21	Slow MA period
Swing fast MA	50	Fast MA period
Swing slow MA	200	Slow MA period

BANDS

Setting	Default	What it does
Bands period	20	Bands period
Bands deviations	2.0	Bands deviations
Bands price	Close price	Bands applied price
Band colour	MediumPurple	Upper / lower band colour
Middle colour	SlateGray	Middle band colour
Bands width	1	Bands line width

FIBO

Setting	Default	What it does
Swing bars	100	Swing high / low from the last N bars
Extensions	true	Show extensions 127.2% / 161.8%
Fibo colour	Gold	Fibonacci colour
Fibo width	1	Fibonacci line width

PIVOTS

Setting	Default	What it does
Pivot formula	Classic	Pivot formula
Pivot period	Auto	Pivot period
Skip weekend candles	true	Skip Sunday / Saturday mini candles
Previous high / low	true	Show previous period high / low
P colour	Silver	Pivot P colour
R colour	Tomato	R1-R3 colour
S colour	MediumSeaGreen	S1-S3 colour

Setting	Default	What it does
High / low colour	SteelBlue	Previous high / low colour
Pivot width	1	Pivot line width

SESSIONS (GMT)

Setting	Default	What it does
Box style	Outline	Session box style
Days	5	Days to show
Auto GMT offset	true	Detect broker GMT offset automatically
GMT offset (h)	2	Broker GMT offset (hours) if auto is off / unknown
Asia start	0	Asia start hour (GMT)
Asia end	9	Asia end hour (GMT)
London start	7	London start hour (GMT)
London end	16	London end hour (GMT)
New York start	12	New York start hour (GMT)
New York end	21	New York end hour (GMT)
Summer time	true	+1 h in winter (auto)
Asia colour	DodgerBlue	Asia colour
London colour	Goldenrod	London colour
New York colour	MediumOrchid	New York colour

S/R ZONES

Setting	Default	What it does
Look back bars	300	Look back N bars
Swing strength	5	Swing strength (bars each side)
Zone width (ATR)	0.5	Zone width (x ATR 14)
Min swings	2	Min swings in a zone
Max zones	6	Max zones shown
Resistance colour	Tomato	Resistance zone colour
Support colour	MediumSeaGreen	Support zone colour

OSC

Setting	Default	What it does
RSI period	14	RSI period
RSI overbought	70.0	RSI overbought (red)
RSI oversold	30.0	RSI oversold (green)
MACD fast	12	MACD fast EMA
MACD slow	26	MACD slow EMA
MACD signal	9	MACD signal period

Setting	Default	What it does
ATR period	14	ATR period
Stoch %K	5	Stochastic %K period
Stoch %D	3	Stochastic %D period
Stoch slowing	3	Stochastic slowing
Stoch overbought	80.0	Stochastic overbought (red)
Stoch oversold	20.0	Stochastic oversold (green)
Bias votes (of 4)	3	Votes of 4 for BULL / BEAR (RSI>50, MACD hist>0, %K>%D, close>slow MA)

SUPPLY / DEMAND

Setting	Default	What it does
Look back bars	1000	Look back N bars
Zone fuzz	0.5	Zone fuzz factor (x half ATR 7)
Fast swing	7	Fast swing (bars each side)
Slow swing	15	Slow swing (bars each side)
Weak zones	true	Show weak zones
Untested zones	true	Show untested zones
Turncoat zones	true	Show turncoat (flipped) zones
Merge zones	true	Merge overlapping zones
Extend zones	true	Extend zones by the fuzz
Zone labels	true	Zone labels (strength + retests)
Supply colour	Crimson	Supply (resistance) colour
Demand colour	SeaGreen	Demand (support) colour
Turncoat colour	DarkOrange	Turncoat zone colour

NEURAL

Setting	Default	What it does
Past bars	100	Past bars fitted
Future bars	40	Bars projected past the last bar
Harmonics	40	Harmonics (sine waves) fitted
Draw fit	false	Also draw the fitted curve over the past bars
Forecast colour	Red	Forecast colour

ELLIOTT

Setting	Default	What it does
Swing depth	6	Swing depth (bars each side)
Min move (points)	5	Min move between pivots (points)
Pivots labelled	14	Recent pivots labelled

Setting	Default	What it does
Look back bars	500	Look back N bars
Zigzag	true	Draw the zigzag between pivots
Fibo on last leg	true	Fibonacci retracement on the last leg
Targets	true	Target projections
Trend line	true	Elliott trend / base line
High label colour	OrangeRed	High-pivot label colour
Low label colour	LimeGreen	Low-pivot label colour
Target colour	Aqua	Target colour
Trend colour	Lime	Trend line colour
Zigzag colour	DodgerBlue	Zigzag colour
Fibo colour	Goldenrod	Fibonacci colour

CLUSTER

Setting	Default	What it does
Cluster bars	30	Newest visible bars drawn as clusters
Row height (points)	0	Row height in points (0 = auto from ATR)
Max rows	20	Max rows per bar
Volume numbers	true	Volume numbers in the cells (when zoomed in)
Volume profile	true	Volume profile right of the last bar
Build from M1	true	Build the cells from M1 bars (else from the bar's own range)

ALERTS

Setting	Default	What it does
Alerts	false	Alerts on (panel ALERTS button)
Level alerts	true	Alert when price reaches a pivot / fibo / zone
MA cross alerts	true	Alert on fast / slow MA cross (closed bar)
Phone push	false	Also send a push notification to the phone

16. Troubleshooting

Problem	What to do
Nothing happens on START / PLACE	The AutoTrading button is off or "Allow live trading" is not ticked on the robot's Common tab.
A project shows ERROR in the list	It could not start with its settings (for example Copier SLAVE without a key, Telegram without a token, AI without an API key). Open it, fix the settings in SETTINGS > or the Inputs and press APPLY / OK.
A project does not open new trades	RUN = ONLY THE CHOSEN PROJECT and the project is not on the panel. Put it on the panel or switch RUN to ALL PROJECTS TOGETHER.
The project list opens on every attach	That is the first-attach list. After you choose, it does not open again on a timeframe change or restart. Removing the robot from the chart starts fresh.
WebRequest error 4060 / 5203	The address is not allowed. Add it in Tools → Options → Expert Advisors (section 3 d), exactly as written.
Telegram or AI stopped answering	They work only while they are on the panel. Put them on the panel again.
Panel too big for the chart	Use HIDE, move it with RIGHT > / < LEFT, or make the chart window bigger.
Chart colours changed	The theme sets TradingView colours. Set COMMON Chart style to Keep my chart to keep your own colours.
Panel buttons do not react	The robot is not running on this chart. Remove it (right-click the chart → Expert list → Remove), refresh the Navigator and attach it again. The Experts tab shows the reason.

Where to look

- **Experts tab** (Terminal window) – every action of every project, with its name.
- **Journal tab** – platform messages, for example connection or trading permission problems.
- **Status line** – the bottom line of each panel says what the project did last or why it waits.

17. Risk warning

Trading leveraged products such as gold and currencies carries a high risk of loss. Martingale baskets and stop order grids add orders while the price moves; a long one-way move or a news spike can produce a large loss. Copied trades and AI answers can be wrong. Past results do not guarantee future results. Start on a demo account, use small lots, set the limits you can carry and only trade money you can afford to lose. The author is not responsible for losses caused by using this software.

18. Support and links

Questions, ideas or a problem? Send screenshots of the Experts and Journal tabs, of the project panel and of the robot's Inputs tab to our Telegram channel.

Link	Address
Website	https://polymaria.net
Telegram channel	https://t.me/polymaria_net
All products on MQL5	https://www.mql5.com/en/users/murodillo/seller